

Guidebook for iPhone


Installation guide and setting BRIA for iPhone

INSTALLATION


1. Go to the App Store and search for the application Bria. Then proceed to the purchase and installation after which the application icon will appear.



2. Proceed to the purchase of the G.729 codec by going to Settings, and then click Premium Features.




3. Click on the item G729 Audio Codec and purchasing. To confirm the installation you will see a "?" on the left side of the codec.



CONFIGURATION

1. Click on the icon Bria and enter a new VoIP account by clicking on "VoIP (SIP) - Calling".



2. Fill in the fields as follows:

- Account Name: VoipTel
- Display As: Account number or VoIP phone number of Easy-VoipTel
- Username: VoIP account number or phone number of Easy-VoipTel
- Password: The password or User Account VoIP Easy-VoipTel
- Domain: voip.swissvoiptel.ch or the domain name of the PBX Easy-VoipTel
- VM Number: 777
- Enables Switch to ON 3

Annulla		New SIP Account	Salva
Account Name	VoipTel		
USER DETAILS			
Display as	123456		
Username	123456		
Password	●●●●●●●●●●●●●●●●		
Domain	voip.swissvoiptel.ch		
Enabled <input checked="" type="checkbox"/>			
VOICE MAIL			
VM Number	777		


- Completed data entry you can save your settings by pressing the Save button and allow the registration of the account.

< Settings	Accounts	+
Enabled		
→	VoipTel	


- Returning to the main menu and selecting the Settings tab you can customize the application click Preferences. Verify that the entries Use When Available, Allow VoIP Calls and Run in Background are abilitate

< Settings	Preferences
MOBILE DATA NETWORK	
Use When Available	<input checked="" type="checkbox"/>
Allow VoIP Calls	<input checked="" type="checkbox"/>
Enable to allow Bria to use your mobile data plan when Wi-Fi is not available.	
GENERAL	
Run In Background	<input checked="" type="checkbox"/>

5. Returning to the main menu and selecting the Settings tab you can customize the application click Advanced Settings. Verify that the Voice Activity Detection is disabled and removed Quality Of Service and Noise Reduction Tx are enabled.



6. Selecting the items and Mobile Wi-Fi Audio Codecs Audio Codecs sure they are enabled only - WB codec G722, G729a, G711u, GSM and arrange them in this order by pressing and holding the button on the right and moving it up or down. Returning to the main menu, press Yes to apply your changes.



Rev. 07.08.14